



The Abdus Salam
International Centre
for Theoretical Physics

Running WRF-Sfire with real data

Adam Kochanski

Jan Mandel

Jonathan Beezley




Running WRF-Sfire with real data

Process of running real WRF-Sfire case is very similar to running the regular WRF and consists of the following steps:

1. Getting needed data
2. Defining the domain setup in `namelist.wps`
3. linking meteorological files in grib format using `linkgrib.sh`
4. Uncompressing (ungribing) meteorological files using `ungrib.exe`
5. Preparing high-resolution fire data using `convert_geotiff`
6. Preparing `geo_em.d0X` files containing all static data for the WRF domains using `geogrid.exe`
7. Interpolating meteorological data to WRF domains defined by `geo_em.d0X` files using `metgrid.exe`
8. Defining simulation setup in `namelist.input` and `namelist.fire` and creating `wrfinput_d0X` and `wrfbdy_d0X` files using `real.exe`

Running WRF-Sfire with real data





Obtaining data for geogrid

- Geogrid needs the static data available from:

http://www2.mmm.ucar.edu/wrf/src/wps_files/geog_v3.1.tar.gz

- This dataset must be extracted (tar -xvf geog_v3.1.tar.gz)

- Its location must be specified as geog_data_path in namelist.wps


for instance:

geog_data_path = /home/jsmith/geog/

- additionally high resolution elevation data and fuel data are needed in geotiff format
- for US they are available from: <http://landfire.cr.usgs.gov/viewer/>

Obtaining fire data for geogrid


<http://landfire.cr.usgs.gov/viewer/>





Obtaining fire data for geogrid


<http://landfire.cr.usgs.gov/viewer/>





Obtaining fire data for geogrid

<http://landfire.cr.usgs.gov/viewer/>





Obtaining fire data for geogrid

landfire.cr.usgs.gov/Website/distreq/RequestOptions.jsp

us_130 Succession Classes			
		NOT SELECTED.	
<input checked="" type="checkbox"/>	us_130 13 Fire Behavior Fuel Models-Anderson	GeotIFF_with_attribs	ZIP
<input type="checkbox"/>	us_130 40 Fire Behavior Fuel Models-Scott/Burgan	Not selected.	
<input type="checkbox"/>	us_130 Biophysical Settings	Not selected.	
<input type="checkbox"/>	us_130 Environmental Site Potential	Not selected.	
<input type="checkbox"/>	us_130 Existing Vegetation Cover	Not selected.	
<input type="checkbox"/>	us_130 Existing Vegetation Height	Not selected.	
<input type="checkbox"/>	us_130 Existing Vegetation Type	Not selected.	
<input type="checkbox"/>	us_130 Fire Regime Groups	Not selected.	
<input type="checkbox"/>	us_130 Forest Canopy Base Height	Not selected.	
<input type="checkbox"/>	us_130 Forest Canopy Bulk Density	Not selected.	
<input type="checkbox"/>	us_130 Forest Canopy Cover	Not selected.	
<input type="checkbox"/>	us_130 Forest Canopy Height	Not selected.	
<input type="checkbox"/>	us_130 LCP 13 Fire Behavior Fuel Models-Anderson	Not selected.	
<input type="checkbox"/>	us_130 LCP 40 Fire Behavior Fuel Models-Scott/Burgan	Not selected.	
<input type="checkbox"/>	us_130 Mean Fire Return Interval	Not selected.	
<input type="checkbox"/>	us_130 Percent Low-severity Fire	Not selected.	
<input type="checkbox"/>	us_130 Percent Mixed-severity Fire	Not selected.	
<input type="checkbox"/>	us_130 Percent Replacement-severity Fire	Not selected.	
<input type="checkbox"/>	us Aspect	Not selected.	
<input checked="" type="checkbox"/>	us Elevation	GeotIFF	ZIP
<input type="checkbox"/>	us Slope	Not selected.	
<input type="checkbox"/>	Fire Planning Units	Not selected.	
<input type="checkbox"/>	LANDFIRE Zones	Not selected.	
<input type="checkbox"/>	LANDFIRE ECOMAP Subsections Map	Not selected.	

Delivery Options:

Maximum size (MB) per piece:

[Cancel All Changes & Return to Summary](#) [Save Changes & Return to Summary](#)



Converting fire data to WPS format

- Conversion of the fuel data and high resolution topography can be performed using convert_geotiff program available from https://github.com/jbeezley/convert_geotiff

- Conversion of the fuel data provided in geotiff format can be performed using the following command:

```
./convert_geotiff.x -c 13 -w 1 -u "fuel category" -d  
"Anderson 13 fire behavior categories" ../your_fuel.tiff
```

- Conversion of the high resolution topography provided as a geotiff file can be performed similarly using the following command:

```
./convert_geotiff.x -u meters -d 'National Elevation Dataset  
1/3 arcsecond resolution' ../your_elevation.tiff
```

- note that convert_geotiff.x should be executed from the locations where the fuel and elevation data are to be stored



Converting fire data to WPS format

- convert_geotiff works should support all WRF projections but lat-lon is the safest choice EPSG 4326 WGS84.
- Convert_geotiff will generate an index file and a set of files in WPS intermediate format containing the fuel and elevation data ready to be processed by geogrid.exe
- Here is an example of the content of the folder where convert_geotiff generated a set of WPS intermediate files:



Converting fire data to WPS format

The index file for fuel should look like below:

```
projection = albers_nad83
truelat1 = 29.500000
truelat2 = 45.500000
stdlon = -96.000000
known_x = 1
known_y = 606
known_lat = 39.747818
known_lon = -107.373398
dx = 3.000000e+01
dy = 3.000000e+01
type = categorical
signed = yes
units = "fuel category"
description = "Anderson 13 fire behavior categories"
wordsize = 1
tile_x = 100
tile_y = 100
tile_z = 1
category_min = 1
category_max = 14
tile_bdr = 3
missing_value = 0.000000
scale_factor = 1.000000
row_order = bottom_top
endian = little
```



Domain configuration in WPS

- The physical domain is configured in the geogrid section of namelist.wps in the WPS directory. In this section, you should define the geographic projection with map_proj, truelat1, truelat2, and stand_lon. Available projections include 'lambert', 'polar', 'mercator', and 'lat-lon'.
- The lower left corner of the domain is located at ref_lon longitude and ref_lat latitude. The computational grid is defined by e_we/e_sn, the number of (staggered) grid points in the west-east/south-north direction, and the grid resolution is defined by dx and dy in meters.
- We also specify a path to where we will put the static dataset that geogrid will read from, and we specify the resolution of the data we plan to use.

```
&geogrid
  e_we                = 43,
  e_sn                = 43,
  geog_data_res       = '30s',
  dx = 60,
  dy = 60,
  map_proj  = 'lambert',
  ref_lat   = 39.70537,
  ref_lon   = -107.2907,
  truelat1  = 39.338,
  truelat2  = 39.338,
  stand_lon = -106.807,
  geog_data_path = '../wrfdata/geog'
/
```



configuration in namelist.input

```
&time_control
run_days = 0,
run_hours = 0,
run_minutes = 20,
run_seconds = 0,
start_year = 2006, 0001, 0001,
start_month = 02, 01, 01,
start_day = 23, 01, 01,
start_hour = 12, 00, 00,
start_minute = 43, 01, 01,
start_second = 00, 00, 00,
end_year = 2006, 0001, 0001,
end_month = 02, 01, 01,
end_day = 23, 01, 01,
end_hour = 13, 00, 00,
end_minute = 00, 600, 600,
end_second = 0, 00, 00,
history_interval_s = 5, 30, 30,
frames_per_outfile = 1000, 1000, 1000,
restart = .false.,
restart_interval = 5
io_form_history = 2
io_form_restart = 2
io_form_input = 2
io_form_boundary = 2
debug_level = 1
/
d01 d02 d03
```



configuration in namelist.input

&domains

```
time_step = 0,  
time_step_fract_num = 3,  
time_step_fract_den = 10,  
max_dom = 1,  
s_we = 1, 1, 1,  
e_we = 20, 43, 43,  
s_sn = 1, 1, 1,  
e_sn = 32, 43, 43,  
s_vert = 1, 1, 1,  
e_vert = 41, 41, 41,  
dx = 50, 30, 10,  
dy = 50, 30, 10,  
ztop = 600, 1500, 1500,  
grid_id = 1, 2, 3,  
parent_id = 0, 1, 2,  
i_parent_start = 0, 1, 1,  
j_parent_start = 0, 1, 1,  
parent_grid_ratio = 1, 2, 3,  
parent_time_step_ratio = 1, 2, 3,  
feedback = 1,  
smooth_option = 0  
sr_x = 10, 0, 0  
sr_y = 10, 0, 0
```

/



configuration in namelist.input

```
&physics
  mp_physics = 1,      1,      1,
  ra_lw_physics = 1,      1,      1,
  ra_sw_physics = 1,      1,      1,
  radt = 30,      30,      30,
  sf_sfclay_physics = 1,      1,      1,
  sf_surface_physics = 1,      1,      1,
  bl_pbl_physics = 1,      1,      1,
  bldt = 0,      0,      0,
  cu_physics = 1,      1,      0,
  cudt = 0,      0,      0,
  isfflx = 1,
  ifsnow = 1,
  icloud = 1,
  num_soil_layers = 5,
  mp_zero_out = 0,
/
```



configuration in namelist.input

&dynamics

```
rk_ord                      = 3,
diff_opt                     = 2,
km_opt                       = 2,
damp_opt                      = 2,
zdamp                         = 5000.,   5000.,   5000.,
dampcoef                      = 0.2,     0.2,     0.2
khdif                          = 0.05,    0.05,    0.05,
kvdif                          = 0.05,    0.05,    0.05,
smdiv                          = 0.1,     0.1,     0.1,
emdiv                          = 0.01,    0.01,    0.01,
epssm                          = 0.1,     0.1,     0.1
mix_full_fields                = .true.,   .true.,   .true.,
non_hydrostatic                 = .true.,   .true.,   .true.,
h_mom_adv_order                 = 5,       5,       5,
v_mom_adv_order                 = 3,       3,       3,
h_sca_adv_order                  = 5,       5,       5,   Tracer for smoke
v_sca_adv_order                  = 3,       3,       3,   representation
time_step_sound                   = 20,      20,      20,
moist_adv_opt                     = 1,       1,       1,   (requires
scalar_adv_opt                     = 1,       1,       1,
tracer_opt                      = 2,       2,       2,   namelist.fire_emissions)
/
```



configuration in namelist.input

```
&bdy_control
periodic_x = .false., .false., .false.,
symmetric_xs = .false., .false., .false.,
symmetric_xe = .false., .false., .false.,
open_xs = .false., .false., .false.,
open_xe = .false., .false., .false.,
periodic_y = .false., .false., .false.,
symmetric_ys = .false., .false., .false.,
symmetric_ye = .false., .false., .false.,
open_ys = .false., .false., .false.,
open_ye = .false., .false., .false.,
spec_bdy_width = 5,
spec_zone = 1,
relax_zone = 4,
specified = .true., .false., .false.,
nested = .false., .true., .true.,
/
/
```

settings
for
ideal
cases



configuration in namelist.input

Fire model will be run in d03 in this case



```

&fire
ifire           = 0, 0, 2,      ! integer, = 0: no fire, = 2: SFIRE
fire_fuel_read = 0, 0,-1,     ! integer, -1: read in from wrfinput
fire_fuel_cat   = 3,          ! integer, if specified which fuel category?

! ignition

fire_num_ignitions = 0, 0, 1, ! integer, only the first fire_num_ignition used, up to 5
fire_ignition_start_lon1= 0, 0,-107.293, ! start points of ignition lines, longitude
fire_ignition_start_lat1 = 0, 0, 39.6986, ! start points of ignition lines, latitude
fire_ignition_end_lon1 = 0, 0,-107.293, ! end points of ignition lines
fire_ignition_end_lat1 = 0, 0, 39.7109, ! end points of ignition lines
fire_ignition_radius1 = 0, 0, 18, ! all within this radius (m) will ignite, > fire mesh
step
fire_ignition_start_time1 = 0, 0, 2, ! sec for ignition from the start
fire_ignition_end_time1 = 0, 0, 2 ! sec for ignition from the start

! Ignition parameters set for the fire domain only

fire_topo_from_atm= 0, 0, 0,    ! 0 = expect fire mesh topo , 1 = from atmosphere
fmoist_run =      .false., .false., .true.,
fmoist_interp =   .false., .false., .true.,
fire_fmc_read =   0, 0, 0,      ! 0 not set use wrfinput, 1 from namelist.fire, 2 read from file
in ideal!

```



Ignition parameters set for the fire domain only



Setting up geogrid to process fire data

All the static data being processed by geogrid.exe are defined in GEOGRID.TBL

In order to enable fire data processing in geogrid.exe :

1. GEOGRID.TBL should be linked to GEOGRID.TBL.FIRE
ln -s GEOGRID.TBL.FIRE GEOGRID.TBL or copied to WPS directory

2. Fuel and high-resolution height section of GEOGRID.TBL have to be edited so the paths correspond to the actual locations of fuel and elevation data processed using convert_geotiff (in our case ned_data, landfire_data)



Setting up geogrid to process fire data

Editing GEOGRID.TBL (WPS/geogrid/GEOGRID.TBL)

=====

```
name=NFUEL_CAT
    priority=1
dest_type=categorical
dominant_only=NFUEL_CAT
z_dim_name=fuel_cat
halt_on_missing=yes
interp_option=default:nearest_neighbor
abs_path=./path_to_your_fuel_data
subgrid=yes
```

=====

```
name=ZSF
    priority = 1
dest_type = continuous
df_dx=DZDXF
df_dy=DZDYF
smooth_option = smth-desmth_special; smooth_passes=1
halt_on_missing=yes
interp_option = default:average_gcell(4.0)+four_pt+average_4pt
abs_path=./path_to_your_elevation_data
subgrid=yes
```

=====



Domain configuration in WPS

- The share section of the namelist.wps defines the fire subgrid refinement in `subgrid_ratio_x` and `subgrid_ratio_y`. This means that the fire grid will be a 10 time refined grid at a resolution of 6 meters by 6 meters. The `start_date` and `end_date` parameters specify the time window that the simulation will be run in. Atmospheric data must be available at both temporal boundaries. The `interval_seconds` defines the time interval between atmospheric data. For our example, we will be using the NARR dataset which is released daily every three hours or 10,800 seconds.

&share

```
wrf_core = 'ARW',
max_dom = 1,
start_date = '2005-08-28_12:00:00',
end_date   = '2005-08-28_15:00:00',
interval_seconds = 10800,
io_form_geogrid = 2,
subgrid_ratio_x = 10,
subgrid_ratio_y = 10,
/
```



Domain configuration in WPS

Once the domain(s) is (are) configured in `namelist.wps` the `geogrid.exe` can be executed in order to process static data.

Typing:

```
./geogrid.exe
```

should start geoegrid and generate a set of `geo_em.d0X.nc` files in the number corresponding to the number of domains configured in `namelist.wps` (paramter `max_dom`)


Open generated `geo_em.d0X.nc` files and verify that the data got processed correctly (check `NFUEL_CAT`, `ZSF` etc)



Processing meteorological data

In real cases WRF need meteorological data in order to generate initial and boundary conditions:

`wrfinput_d01`
`wrfinput_d02`
...
`wrfinput_d0X`
`wrfbdy_d02`



The diagram shows five file names listed vertically. A blue curly brace on the right side groups the first four files: `wrfinput_d01`, `wrfinput_d02`, ..., and `wrfinput_d0X`. To the right of this brace is the text "initial conditions". Below the brace is another blue curly brace that groups the last two files: `wrfinput_d02` and `wrfbdy_d02`. To the right of this second brace is the text "boundary conditions".

Preparation of the meteorological data is done in two steps:

1. Ungribing meteorological files provided in grib or grib2 format which is done by **ungrib.exe**
2. Horizontal interpolation of the meteorological data to WRF domains defined by **geo_em.d0X.nc** files generated earlier which is performed by **metgrid.exe**.



Processing meteorological data

Before the ungrib can decompress grib meteorological files they must be linked to the location where `ungrib.exe` is running.

The linking is performed using the `linkgrib.sh` script:

```
./link_grib.csh path_to_your_grib_files
```

This command should generate links to your grib files in a form:

`GRIBFILE.AAA -> your_metfile1.grb2`

`GRIBFILE.AAB -> your_metfile2.grb2`

`GRIBFILE.AAC -> your_metfile3.grb2`

...

Before running `ungrib.exe` make sure the correct Vtable is linked to your directory. For instance, if you are using NARR data you link

`./ungrib/Variable_Tables/Vtable.NARR` to your WPS directory by typing:

```
ln -s ./ungrib/Variable_Tables/Vtable.NARR ./Vtable
```

you should have now in your WPS directory:

```
Vtable -> ./ungrib/Variable_Tables/Vtable.NARR
```



Processing meteorological data

Once the met files and Vtable are linked you can ready to ungrid your met data (create intermediate met files in WPS format). The name of the output intermediate files are defined in the ungrid section of namelist.wps

```
&ungrib
  out_format = 'WPS',
  prefix = 'NARR_b',
! prefix = 'NARR_a',
/
```

Executing: ./ungrib.exe will start ungridding process which will generate intermediate met files:

```
NARR_a:2012-06-23_18
NARR_a:2012-06-24_00
NARR_a:2012-06-26_06
```

...



Processing meteorological data

Once the intermediate met files are generated, they are ready to be processed further by `metgrid.exe`.

Executing:

```
./metgrid.exe
```

should generate a list of `met_em.d0X` files:

`met_em.d01.2012-06-23_00:00:00.nc`

`met_em.d01.2012-06-23_06:00:00.nc`

`met_em.d01.2012-06-23_12:00:00.nc`

...

The next step is generating the WRF input files from `met_em` files using `real.exe` in `./wrf-fire/WRFV3/test/em_real/` directory



Processing meteorological data

Before `real.exe` is executed, all simulation parameters must be set in `namelist.input`, similarly as it was done for WPS in `namelist.wps`

Once the simulation parameters are set, the WRF input files are generated from `met_em` files using `real.exe` in `./wrf-fire/WRFV3/test/em_real/` directory.

After execution of `real.exe` the following set of files should be generated:

`wrfinput_d01`

`wrfinput_d02`

`wrfinput_d03`

...

`wrfdy_d01`

the next step after generating these files is configuring fire parameters in `namelist.fire` and running `wrf.exe`

Configuration of fire parameters in namelist.fire

```
&fuel_scalars
  cmbcnst = 17.433e+06,                                ! scalar fuel constants
  hfgl    = 17.e4 ,                                     ! J/kg combustion heat dry fuel
  fuelmc_g = 0.18,                                      ! W/m^2 heat flux to ignite canopy
  !jc fuelmc_g = 0.09,                                   ! ground fuel moisture, set = 0 for dry
  fuelmc_c = 1.00,                                      ! ground fuel moisture, set = 0 for dry
  nfuelscats = 13,                                       ! canopy fuel moisture, set = 0 for dry
  no_fuel_cat = 14,                                      ! number of fuel categories used
  /                                                       ! extra category for no fuel

&fuel_categories
  fuel_name =
  '1: Short grass (1 ft)',
  '2: Timber (grass and understory)',
  '3: Tall grass (2.5 ft)',
  '4: Chaparral (6 ft)',
  '5: Brush (2 ft) ',
  '6: Dormant brush, hardwood slash',
  '7: Southern rough',
  '8: Closed timber litter',
  '9: Hardwood litter',
  '10: Timber (litter + understory)',
  '11: Light logging slash',
  '12: Medium logging slash',
  '13: Heavy logging slash',
  '14: no fuel'
```



Configuration of fire parameters in namelist.fire

```
fmc_gw01 = 1.00000, 0.15385, 1.00000, 0.31253, 0.28571, 0.25000, 0.23203,  
          0.30000, 0.06625, 0.25042, 0.13021, 0.11600, 0.12065, 0.00000,  
fmc_gw02 = 0.00000, 0.07692, 0.00000, 0.25016, 0.14286, 0.41667, 0.38398,  
          0.20000, 0.93034, 0.16639, 0.39149, 0.40584, 0.39656, 0.00000,  
fmc_gw03 = 0.00000, 0.38462, 0.00000, 0.12477, 0.00000, 0.33333, 0.30801,  
          0.50000, 0.00341, 0.41680, 0.47830, 0.47816, 0.48279, 0.00000,  
fmc_gw04 = 0.0, 0.0, 0.0, 0.0, 0.0, 0.0, 0.0,  
          0.0, 0.0, 0.0, 0.0, 0.0, 0.0, 0.0,  
fmc_gw05 = 0.00000, 0.38462, 0.00000, 0.31254, 0.57143, 0.00000, 0.07598,  
          0.00000, 0.00000, 0.16639, 0.00000, 0.00000, 0.00000, 0.00000,  
/  
&moisture  
moisture_class_name =  
'1 hour fuel',  
'10 hour fuel',  
'100 hour fuel',  
'1000 hour fuel',  
'live fuel'  
moisture_classes=      5,  
drying_model=         1,      1,      1,      1,      1, ! number of model - only 1= equilibrium  
moisture Van Wagner (1972) per Viney (1991) allowed  
drying_lag=           1,      10,     100,    1000,    1e9, ! so-called 10hr and 100hr fuel  
wetting_model=        1,      1,      1,      1,      1, !  
wetting_lag=          14,    1e9,    1e9,    1e9,    1e9, ! 14 is calibrated to  
VanWagner&Pickett 1985, Canadian fire danger rating system  
saturation_moisture=  2.5,    2.5,    2.5,    2.5,    2.5, !  
saturation_rain =     8.0,    8.0,    8.0,    8.0,    8.0, ! (mm/h)  
rain_threshold =      0.05,   0.05,   0.05,   0.05,   0.05, ! mm/h rain too weak to wet anything.  
fmc_gc_initialization = 0,      0,      0,      0,      0, ! 0 = from input, 1 = from fuelmc_g in  
namelist.input 2 = from equilibrium  
/
```



Configuration of emission parameters

in namelist.fire_emissions

Depending on the level of chemistry used appropriate namelist.fire_emissions file must be used. For no-chemistry runs, only passive tracer option is available.

To use passive tracers for smoke visualization (no chemistry) make sure you link appropriate emission configuration file:

namelist.fire_emissions -> namelist.fire_emissions.tracers

&emissions

```
! Tracer emissions table
! Classification:Grasslands,Grasslands,Grasslands,Open Shrublands,Open Shrublands,Open
Shrublands,Open Shrublands,Mixed Forests,Mixed Forests,Mixed Forests,Evergreen Forest,Evergreen
Forest,Evergreen Forest,
compatible_chem_opt=0,
printsums=1, ! print sums of fuel burned and total emitted into the atmosphere
Fuel Cat, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13,
! tracer emissions [g/kg burnt]
tr17_1=59,59,68,68,68,68,102,102,102,118,118,118
tr17_2=59,59,68,68,68,68,102,102,102,118,118,118
tr17_3=59,59,68,68,68,68,102,102,102,118,118,118
tr17_4=59,59,68,68,68,68,102,102,102,118,118,118
tr17_5=59,59,68,68,68,68,102,102,102,118,118,118
tr17_6=59,59,68,68,68,68,102,102,102,118,118,118
tr17_7=59,59,68,68,68,68,102,102,102,118,118,118
tr17_8=59,59,68,68,68,68,102,102,102,118,118,118
```

That is the place to define your tracer emission factors



Running WRF-Sfire in real cases

- If you have:
 - generated wrfinput_d0X and wrfbdy_d01 files
 - make sure the fire data are there (NFUEL_CAT, ZSF)
 - configure your meteorological and fire parameters in namelist.input and nemelist.fire
 - You are ready to start your simulation executing:
./wrf.exe



Experiment6

1. Go to WPS directory
2. Copy files to WPS folder
3. Untar NARR, fuel and topo data
4. Run geogrid.exe (generation of geo_em.d01.nc ...)
5. Link Vtable
6. Link NARR_a met data
7. Link NARR_b met data
8. Run ungrid.exe (generation of NARR_a/b interm. files)
9. Run metgrid.exe (generation of met_em.d01_xx files)
10. Run real.exe (generation of wrfinput and wrfbdy files)
11. Run wrf.exe



Experiment6

1. Go to /scratch/wrf-fire/WPS

2. Copy files to WPS folder:

```
cp /home/netapp-clima-scratch/smr2717/lab_sessions/Experiment6/namelist.wps .
cp /home/netapp-clima-scratch/smr2717/lab_sessions/Experiment6/namelist.input .
cp /home/netapp-clima-scratch/smr2717/lab_sessions/Experiment6/NARR.tgz .
cp /home/netapp-clima-scratch/smr2717/lab_sessions/Experiment6/landfire_data.tgz .
cp /home/netapp-clima-scratch/smr2717/lab_sessions/Experiment6/ned_data.tgz .
cp /home/netapp-clima-scratch/smr2717/lab_sessions/Experiment6/GEOGRID.TBL .
```

3. Untar NARR fuel and topo data

```
tar -xvf NARR.tgz
tar -xvf landfire_data.tgz
tar -xvf ned_data.tgz
```

4. Run ./geogrid.exe

it should generate:

```
geo_em.d01.nc geo_em.d02.nc geo_em.d03.nc geo_d04.nc
```

5. Link Vtable:

```
ln -s ./ungrib/Variable_Tables/Vtable.NARR ./Vtable
```

6. Link NARR_a met data

```
./linkgrib ./NARR_a/*
```



Experiment6

6. Link NARR_a met data

```
./linkgrib ./NARR_a/*
```

That will generate a lot of GRIBFILE links:

GRIBFILE.AAA	GRIBFILE.AAE	GRIBFILE.AAI	GRIBFILE.AAM
GRIBFILE.AAB	GRIBFILE.AAF	GRIBFILE.AAJ	GRIBFILE.AAN
GRIBFILE.AAC	GRIBFILE.AAG	GRIBFILE.AAK	GRIBFILE.AAO
GRIBFILE.AAD	GRIBFILE.AAH	GRIBFILE.AAL	GRIBFILE.AAP

7. Modify namelist.wps (f.e emacs namelist.wps) to have:

```
end_date = '2012-06-24_18:00:00', '2012-06-24_18:00:00',  
'2012-06-24_18:00:00', '2012-06-24_18:00:00',
```

8. Run ungrib to extract the met data

```
./ungrib.exe
```

That will generate ungribed NARR_a files:

```
NARR_a:2012-06-23_18  
NARR_a:2012-06-24_00  
NARR_a:2012-06-26_06
```



Experiment6

7. Remove old GRIBFILE links: `rm GRIBFILE.*` and link NARR_b met data

```
./linkgrib ./NARR_b/*
```

That will generate again a lot of GRIBFILE links linked to NARR_b:

GRIBFILE.AAA	GRIBFILE.AAE	GRIBFILE.AAI	GRIBFILE.AAM
GRIBFILE.AAB	GRIBFILE.AAF	GRIBFILE.AAJ	GRIBFILE.AAN
GRIBFILE.AAC	GRIBFILE.AAG	GRIBFILE.AAK	GRIBFILE.AAO
GRIBFILE.AAD	GRIBFILE.AAH	GRIBFILE.AAL	GRIBFILE.AAP

8. Edit namelist.wps

```
emacs namelist.wps
```

change:

```
! prefix = 'NARR_b',  
prefix = 'NARR_a',  
to  
prefix = 'NARR_b',  
! prefix = 'NARR_a',
```

9. Run ungrib again to extract the second set of meteo data

```
./ungrib.exe
```

That will generate ungribed NARR_b files:

```
NARR_b:2012-06-23_18  
NARR_b:2012-06-24_00  
NARR_b:2012-06-26_06
```



Experiment6

10. Link METGRID.TBL to WPS directory:

```
ln -s ./metgrid/METGRID.TBL ./
```

11. Run metgrid.exe

```
./metgrid.exe
```

That will generate a lot of met_em.d0X.xxxx files

12. Go to /wrf-fire/WRFV3/test/em_real/, and copy namelist.input there

```
cd /wrf-fire/WRFV3/test/em_real/  
cp ../../WPS/namelist.input ./
```

13. link met_em files to /wrf-fire/WRFV3/test/em_real/

```
ln -s ../../WPS/met_em.* ./
```

14. Edit namelist.input to set the simulation end time to:

end_year	= 2012,	2012,	2012,	2012,
end_month	= 06,	06,	06,	06,
end_day	= 24,	24,	24,	24,
end_hour	= 06,	06,	06,	06,

15. Run ./real.exe to generate

```
wrfinput_d01, wrfinput_d02, wrfout_d03, wrfinput_d04,  
wrfbdy_d01
```

16. Run wrf.exe